


Before starting, please read all instructions.

**Finished backpack size:**



40 cm high x 30 cm wide x 15 cm (height / width / bottom depth)  
(15,75 x 11,8 x 5,9")

**The backpack requires:**

- contrasting fabric – 70 cm width 140 cm (27,6" width 55")
- fabric with print – 30 cm width 140 cm (11,8" width 55")
- lining fabric – 50 cm width 140 cm (19,7" width 55")

*Note: more fabric may be required if using a directional print.*

- zipper size 3 mm (No 3) or 5 mm (No 5), length 24 cm/9,4" (length of teeth/spiral) – exterior zipper pocket
- zipper size 3 mm (No 3) or 5 mm (No 5), length 55 cm/21,7" (length of teeth/spiral) – top closing of the backpack
- mediumweight interfacing, iron-on, e.g. Ronofix, RONARFIX, fusible fleece, 100 g/m<sup>2</sup> or more – 110 cm width 80 cm (43,3" width 31,5")
- lightweight interfacing, iron-on e.g. Novoplast, Vlieseline, 30 to 60 g/m<sup>2</sup> - 40 cm width 90 cm (15,75" width 35,4")
- 2 x rectangular ring 2,5 cm/1"
- 2 x adjustable strap slider 2,5 cm/1"
- 1 x adjustable strap slider 2 cm/0,8"
- 1 x release buckle 2 cm/0,8"
- threads
- common sewing supplies

## 2.2. Side panels with slide pockets

### Pockets preparation

Prepare two slip pockets. The procedure is the same for both pockets.



The pocket parts are mirror cut.



Place matching fabric pieces (1x fabric with print, 1x contrasting fabric) right sides together. Align the upper sides, fix and sew.



Turn the fabric in the top seam right side up. Topstitch the top edge along the fold. Also sew the sides and bottom together.

