



### **Knitting pattern cable sweater Brenda:**

#### **Information:**

- Sweater Brenda has a beautiful cable pattern in the center of the front and back.
- There are mini cables on the sleeves
- The pattern is available in 5 sizes (S – XXL). See the size chart for more information.
- The sweater is knitted in the round from the bottom up to the armhole. Then the sweater is divided into a front and a back piece and worked flat (back and forth).
- The sleeves are worked in the round from the bottom up
- For the collar at the neck you have to pick up stitches and knit a rib stitch

**Gauge** with knitting needles size 6 (US), 8 (UK) = 4mm in stockinette stitch (knit on right side, purl on wrong side) = 22 stitches and 32 rows = 10 x 10 cm / 4 x 4 inch

**Level:** intermediate: you must have knowledge of knitting in the round, knitting cables, picking up stitches for the neckband.

#### **Materials:**

- Circular knitting needle 4 (US), 9 (UK) = 3.5 mm with a length of 60 cm / 24 inch
- Circular knitting needle 6 (US), 8 (UK) = 4 mm with a length of 60 cm / 24 inch
- The sleeves are also worked in the round with these circular knitting needles. You can use the same (length) circular knitting needles using the magic loop method or else use double pointed needles
- Cable needle
- Needle to sew the sleeves into the sweater
- Yarn with yarn weight sport / 4 ply (I have used Lana Grossa Ecopuno – color 44 mint turquoise)
- For the quantities see the size chart for more information (bottom rows).

**Size chart:**

Sizes	S	M	L	XL	XXL
Size in cm	81-86	91-97	102-107	112-117	122-127
Size in inch	32-34	36-38	40-42	44-46	48-50
<b>Finished Size</b>					
Size in cm	88	98	110	122	136
Size in inch	34.6	38.6	43.3	48	53.5
Length in cm	57.5	59.5	61.5	63.5	65.5
Amount of yarn					
in meters	1205	1325	1510	1640	1800
in yards	1320	1450	1650	1795	1970
skeins Ecopuno	6	7	7	8	9

**Used stitches:**

k = knit, p = purl

C4F: put 2 stitches on a cable needle and hold in front, k2, k2 from cable needle

C4B: put 2 stitches on a cable needle and hold in back, k2, k2 from cable needle

C3F: put 2 stitches on a cable needle and hold in front, p1, k2 from cable needle

C3B: put 1 stitch on a cable needle and hold in back, k2, p1 from cable needle

M1 = Make 1 = increase 1 stitch

MC = explanation mini cable: insert the needle into the next 2 stitches, yarn over, pull the yarn through the 2 stitches, (i.e. just as if you were knitting the 2 stitches together) but leave the 2 knitted stitches on the needle. Insert the knitting needle into the first stitch, so in between the 2 stitches knitted together and wrap the yarn around the needle again and pull the yarn through and let the 2 stitches slip off the left needle.

**Cable patterns:**

**Cable pattern A** is used (after knitting the rib stitch) till the armholes; the sweater is knitted in the round till the armholes.

From the armholes up we knit flat (back and forth) and use **Cable pattern B**