



STEP 4:

You have just cut your pattern pieces. You have a front (piece n°1), a back (piece n°2), 2 front shoulder straps (piece n°4), 2 back shoulder straps (piece n°5), and the back upper part (piece n°3). Assemble the piece n°2 and the piece n°3. The thing is that you do not have to pull the jersey to respect the cut. If it is your first time doing it, train on jersey scraps before doing it on your actual piece. Mark 2 notches with a tailor's chalk, one on the wrong side of the piece n°3 at 0.7cm of the peak and the other on the right side of the piece n°2 at 0.7cm of the peak. These notches will help you to know where you will have to stop sewing to turn the work.



Take the piece n°3 on the wrong side in front of you and lay it on the piece n°2, which has the right side in front of you. Align a side of the yoke, the notches must be on top of each other. The two pieces now have their right sides together, you can pin.

We are going to sew on 3 steps:



First step, the peak. Put the presser foot at 3cm from the peak. Align the edge of the presser foot to the edges of the fabric. Set up your sewing machine for a 3mm long straight stitch (yes, a straight stitch and not a stretch stitch), and the needle must be in the middle (you will have a seam at 0.7cm from the edge).